



Suggested (Default)

User Permission Worksheet w/Suggested Permission Levels Pedz

Maint/Security	STAFF NURSE	SUPER USER	ADMIN	PERMISSIONS	PERMISSION DESCRIPTION
----------------	-------------	------------	-------	-------------	------------------------

NOTE: These permission levels can be renamed

CONFIGURATION ACCESS

X			X	MODIFY CONFIGURATION	The user can change settings in the PS System Manager.
		X	X	ADD/DELETE/EDIT USERS	The user can create, delete, and change user accounts.

LONWORKS NETWORK

X			X	PERFORM LONWORKS NETWORK/TAG DIAGNOSTICS	The User can access the Tag Diagnostics dialog box.
X			X	CHANGE THE LONWORKS NETWORK CONFIGURATION	The User can configure LonWorks devices.

TAGS

X	X	X	X	DISCHARGE TAGS	The user can discharge tags.
X	X	X	X	TRANSPORT TAGS	The user can Transport a patient for a configurable period of time.
X	X	X	X	SUSPEND TAG	The user can suspend the tag.
X			X	MANUAL ADMIT TAGS	The user can manually admit tags.
X	X	X	X	DISPLAY TAG STATUS	The user can check the status of tags in the Census List.
X	X	X	X	DISPLAY TAG HISTORY	The user can check the history of the tags in the Census List.
	X	X	X	EDIT TAG MEMO	The user can create or edit memos for tags.
		X	X	DISCHARGE TAGS W/O FINAL MATCH	The user can discharge a tag from the system without performing a final match of mother and infant. (Requires Kisses Tag)
X	X	X	X	EDIT TAG DESCRIPTIONS	The user can change a tag's description in the Census List.
X	X	X	X	EDIT TAG PROPERTIES	The user can edit the tag properties in the Census List.
X	X	X	X	AUTOMATIC ADMIT TAGS	The user can acknowledge Auto Admit messages and enter information for the patient.

GENERAL SOFTWARE ADMINISTRATION

X			X	EXIT/CLOSE THE APPLICATION	The user can exit the Pedz application software.
				PERFORM BACKUP/RESTORE OPERATIONS	Not used.
X			X	OTHER SOFTWARE ADMINISTRATION FEATURES	The user can perform other routine maintenance, including viewing menu items, accessing Print setup, and changing column widths.
			X	OPEN/HIDE THE ALARM WINDOW	The user can open and hide (minimize) the Alarm window.If this permission is not granted, the Alarm window will stay on top until the alarm is cleared.

OTHER FUNCTIONS

	X	X	X	CLEAR ALARMS/EVENTS	The user can clear alarms in the Alarm window and events from the Event window.
			X	VIEW REPORTS	The user can access the Reports dialog box.
X	X	X	X	CHANGE PASSWORD	The user can change his or her password in the Login dialog box.
X			X	BYPASS THE EXCITER	The user can bypass an Exciter to allow a tag to pass through.
X			X	SEND PAGES	The user can send pages using the Send Page command.
X			X	RESET THE DIGITAL IO OUPUT CHANNEL	The user can reset the Output for an I/O Module.
X	X	X	X	USE CCTV FEATURES	The user has access to integrated CCTV functionality (this is an optional feature). If this permission is not allowed, the user will not see CCTV footage during an alarm.
			X	MUTE ALARMS	The user can mute alarms.

Revised 08/03/10